## **Chapter 16 - Remote Access**


June 1, 2001

PC ANYWHERE MANAGER software makes it possible for jurisdictions that do not have the QVF on-site ("county client jurisdictions") to access their QVF files via remote access. QVF computers that were provided by the state to each county are already equipped with this software. Accessing QVF files via remote, requires the cooperation of the county and each participating local jurisdiction. At this point, no more than one remote user can be connected to the county QVF computer via PC ANYWHERE MANAGER software at any one time. However, we expect that this will change in the near future. Once the remote connection is in place, accessing local QVF files is convenient and easy!

Participating "county client jurisdictions" will need the following: 1.) an IBM compatible Pentium computer, 2.) PC ANYWHERE MANAGER software (version 10 or higher), 3.) a modem, 4.) a telephone line and 5.) Internet access. Accessing the county QVF computer via remote, can be accomplished over the Internet or by directly dialing the county computer. While direct dialing is the quickest way to access the county QVF computer, this could result in long distances charges if the number is not local. In such cases, accessing the county QVF computer over the Internet is recommended. In addition to the above, once connected, participating "county client jurisdictions" may also be able to print reports, forms and other election related files via remote access using a variety of QVF compatible printers.

For more information regarding remote access, please contact the QVF Help Desk.

## Direct Dialing to the County Computer



The first step is to prepare the county QVF computer for the remote connection by completing the following:

Action	Result
On the Windows Main Desktop, double click on	The <b>PC</b> Anywhere Manager screen appears.
the PC Anywhere icon.	
On the <b>PC</b> Anywhere Manager screen, ensure	The <b>PC</b> Anywhere Manager screen drops to
the [Hosts] button is pushed in. Then double	the task bar as an icon in the lower right
click on the <i>Modem</i> (or <i>QVF</i> ) icon.	corner of the screen.
The county computer is now ready to be	
operated by remote control.	
This set up can be left open at night and on	
weekends so remote users can get in at their	
convenience.	

The county may leave the connection open for extended periods. However, in this case, it is recommended that the county QVF computer to be periodically rebooted.




Local remote access jurisdictions initiate the connection by completing the following:

Action	Result
Double click on the <i>PC Anywhere</i> icon in the	The <i>PC Anywhere 32</i> screen or the <i>PC</i>
Windows Main Desktop.	Anywhere Manager screen (in version 10) is
	displayed.
On the <b>PC</b> ANYWHERE screen, ensure the	The <b>PC</b> Anywhere Waiting screen is displayed
[Remotes] or [Remote Control] button is	
pushed in. Then double click on the <i>Modem</i>	
(or QVF) icon.	
In the <i>PC Anywhere Waiting</i> screen, enter the	The <i>Modem-PC ANYWHERE MANAGER</i>
phone number to the county computer and click	screen appears with <i>User Name</i> and
on the [OK] button.	<b>Password</b> screen superimposed.
Enter the log in name and password supplied	After a moment, the <i>County-Co - PC</i>
by the county and click on the <b>[OK]</b> button.	ANYWHERE screen is displayed (Ingham-Cα
	- PC ANYWHERE for example). You are
	now seeing what is on the Windows Main
	Desktop of the county's computer.
Double click on the <i>Michigan QVF</i> icon.	The <i>QVF</i> Application will start running.
Enter the user name and password supplied by	You are logged into the <i>QVF</i> software, and are
the QVF Helpdesk and click on the [Logon]	now able to work in your records.
button.	

When you have finished, close out of the <i>QVF</i>	This will break your connection to the host
using File, then Exit. Click on [X] in the upper	computer.
right hand corner of the <i>PC Anywhere</i> screen	
and click on the <b>[OK]</b> button when the <b>End</b>	
Remote Session screen appears.	


## Internet Connection to the County Computer



The first step is to prepare the county QVF computer for the remote connection by completing the following:

Action	Result
On the Windows Main Desktop double click on	The <i>Connecting Michnet</i> screen appears and
the <i>Dial Michnet</i> ( <i>Dial QVF</i> in some places)	automatically dials the Michnet number.
icon.	
	Your internet connection is established, a
	small <i>Modem</i> icon appears in the task bar in
	the lower right corner of the screen.
Right click on the small <i>Modem</i> icon on the	A menu appears.
taskbar in the lower right corner of the screen.	
Click on <i>Status</i>	The <i>Michnet Status</i> screen is displayed.
Click on the <b>Details</b> tab.	The <i>Details</i> tab appears. The <u>Server IP</u>
	Address (looks like xxx.xxx.xx) needs to
	be given to the remote user when they try to
	connect. (This number will change every time
	you connect.)

After you have noted the IP address, click on the [X] button in the upper right corner of the	The <i>Michnet Status</i> screen closes
screen.	
Double click on the <i>PC Anywhere</i> icon on the	The <b>PC</b> Anywhere Manager screen is
Windows Main Desktop.	displayed.
Double click on the <i>Network</i> or <i>QVF</i> icon.	After a moment a small <b>PC</b> Anywhere icon
	appears on the far right side of the task bar.
The county computer is now ready to be	This connection will last for about twenty
operated by remote control.	minutes of inactivity. It will then disconnect
	from the internet and will need to be
	connected to the internet again.



Local remote access jurisdictions initiate the connection by completing the following:

Action	Result
Establish your internet connection.	
Get the IP address from the county	
On your Windows Main Desktop, double click	The <b>PC</b> Anywhere Manager screen or the <b>PC</b>
on the <b>PC</b> Anywhere icon.	Anywhere 32 screen appears.
Ensure the [Remotes] button or the [Remote	
<b>Control</b> ] button at the top of the screen is	
pushed in.	

Right click on the <i>Network</i> icon. From the drop	The Network Properties screen appears.
down menu click on <i>Properties</i> .	
Click on the <b>Settings</b> tab.	The <b>Settings</b> tab is displayed.
Enter the IP address you received from the	
county in the Network host PC to Control or IP	
address field.	
At the bottom of the <i>Network Properties</i> screen	The <i>Network Properties</i> screen disappears.
click on the [Apply] button, then click on the	
[OK] button.	
On the <b>PC</b> Anywhere screen, double click on the	After a moment, a screen labeled with the
Network icon.	remote computer name ( <i>Ingham-Co</i> for
	example) will appear. This screen will be
	black at first with a request for username and
	password.
Enter the login name and password supplied by	Your screen will show the computer desktop
the county and click on the [OK] button.	of the computer you are networking.
On the Windows Main Desktop of the county	Enter the user name and password supplied by
computer, double click on the <i>QVF</i> icon.	the QVF Helpdesk and click on the [Logon]
	button
	You have complete access to the <i>QVF</i>
	application.
When you have finished, close out of the <i>QVF</i>	The <i>QVF</i> closes.
by clicking on <i>File</i> then <i>Exit</i> .	
Click on the [End Remote Session] button in	You are disconnected from the county
the <b>PC</b> Anywhere screen.	computer.
Disconnect from the internet.	